

I-8017/I-9017 Series Linux API Reference Manual

V 3.0.0 July 2018



Written by Edward Wu
Edited by Anna Huang
Cindy Huang

Warranty

All products manufactured by ICP DAS are under warranty regarding defective materials for a period of one year, beginning from the date of delivery to the original purchaser.

Warning

ICP DAS assumes no liability for any damage resulting from the use of this product. ICP DAS reserves the right to change this manual at any time without notice. The information furnished by ICP DAS is believed to be accurate and reliable. However, no responsibility is assumed by ICP DAS for its use, nor for any infringements of patents or other rights of third parties resulting from its use.

Copyright

Copyright © 2018 by ICP DAS Co., Ltd. All rights are reserved.

Trademarks

Names are used for identification purposes only and may be registered trademarks of their respective companies.

Contact Us

If you have any problems, please feel free to contact us.
You can count on us for a quick response.
Email: service@icpdas.com

Table of Contents

Table of Contents	3
1. Introduction	4
1.1. Specifications	6
1.2. Pin Assignments	8
1.3. Jumper Settings	14
1.4. Wire Connections	19
1.5. Block Diagram	21
2. Quick Start	23
3. Demo Programs	24
4. API References	25
4.1. I8017_Init	26
4.2. I8017_GetFirmwareVersion	27
4.3. I8017_GetLibVersion	28
4.4. I8017_GetSingleEndJumper	29
4.5. I8017_ReadAI	30
4.6. I8017_ReadAI_AVG	32
4.7. I8017_ReadAIHex	34
4.8. I8017_ReadAIHex_AVG	36
4.9. I8017_ReadGainOffset_Info	38
4.10. I8017_Read_mA_GainOffset	40
4.11. I8017_Select_SingleEnd	42
4.12. I8017_Get_D_Sub_Status	43
5. Troubleshooting	45
5.1. Service Request Requirements	46
5.2. What to do when the data read from the module seems unstable	47
Appendix A. Error Code	48

1.Introduction

The I-8017W/I-9017 I/O modules are high performance analog input module, up to 16-channel single-ended or 8-channel differential inputs. It features 14-bit resolution, 100Ks/s sampling rates. It provides isolation protection of 2500 Vrms.

The I-8017 I/O modules can be used to measure both voltage and current source. The I-8017DW and I-8017HCW modules include a Jumper that can be used to set the discrete input circuits to add a 125 Ω resistor, so it's not necessary to add external resistor for Differential input. For the I-8017HW an optional external 125 Ω resistor is required to measure the current source.

Applications

- High speed data acquisition systems
- Process monitoring and control
- Vibration analysis
- Digital pattern generator from the digital I/O port

Applicable Platform table

The following table shows which platform the module applies to.

Platform	OS	Module
XPAC	XP-8000(WES)	I-8017HW/I-8017DW/I-8017HCW
	XP-8000-Atom (WES)	I-8017HW/I-8017DW/I-8017HCW
	XP-8000-WES7 (WES7)	I-8017HW/I-8017DW/I-8017HCW
	XP-8000-CE6 (WinCE 6.0)	I-8017HW/I-8017DW/I-8017HCW
	XP-8000-Atom-CE6 (WinCE 6.0)	I-8017HW/I-8017DW/I-8017HCW
	XP-9000-WES7(WES7)	I-9017/I-9017-15/I-9017C-15
WinPAC	WP-8000 (CE 5.0/7.0)	I-8017HW/I-8017DW/I-8017HCW
	WP-9000-CE7 (CE 7.0)	I-9017/I-9017-15/I-9017C-15
LinPAC	LinPAC-8000(Linux kernel 3.2/4.4)	I-8017HW/I-8017DW/I-8017HCW
	LinPAC-9000(Linux kernel 3.2/4.4)	I-9017/I-9017-15/I-9017C-15
IPAC	iPAC-8000 (MiniOS7)	I-8017HW/I-8017DW/I-8017HCW
	I-8000 (MiniOS7)	I-8017HW/I-8017DW/I-8017HCW

The I-8017DW module is equipped with a D-sub connection, meaning that it can be connected using a 37-pin D-sub Connector, as shown in the image below:



For more detailed information regarding 37-pin D-sub Connectors refer to the models indicated in the table below:

Model	Description
DN-37-A	I/O Connector Block with DIN-Rail Mounting and 37-pin D-sub Connector (Pitch: 5.08 mm)
DN-37-381-A	I/O Connector Block with DIN-Rail Mounting and 37-pin D-sub Connector (Pitch: 3.81 mm)
CA-3705A	Male-Female D-sub Cable 0.5 m
CA-3710A	Male-Female D-sub Cable 1 m
CA-3715A	Male-Female D-sub Cable 1.5 m

1.1. Specifications

I-8017HW/I-8017HCW/I-8017DW


Model	I-8017HW	I-8017DW	I-8017HCW
Analog Output			
Channels	8-ch Differential/16-Single-ended		
Voltage Input Range	±1.25, ±2.5, ±5 V, ±10 V		-
Current Input Range	±20 mA (Requires OptionalExternal 125 Ω Resistor)		±20 mA (Jumper Select)
Resolution	14-bit		
Sample Rate	Single Channel Polling Mode :100K S/s Single Channel Interrupt Mode: 50K S/s 8 channel Scan Mode : 16 K S/s		
Accuracy	0.1% of FSR		
Zero Drift	± 0.1 uV/°C		
Span Drift	± 10 ppm/°C		
ESD Protection	±4 kV Contact for each Terminal		
Input Impedance	20 K, 200 K, 20 M (Jumper Select)		
Input Bandwidth	100 KHz		
Connector	20 Pin Terminal Block		
LED Indicators			
System LED Indicator	1 LED as Power Indicator		
I/O LED Indicator	16 LEDs as User defined Indicators		
Isolation			
Intra-module Isolation, Field-to-Logic	2500 Vrms		
Power			
Power Consumption	2 W Max.		
Mechanical			
Dimension (L x W x H)	102 mm x 30 mm x 115 mm		
Environment			
Operating Temperature	-25 °C ~ +75°C		
Storage Temperature	-30 °C ~ +80°C		
Humidity	10% ~ 90% RH, non-condensing		

I-9017/I-9017-15/I-9017C-15

Model	I-9017	I-9017-15	I-9017C-15
Analog Output			
Channels	8 Differential/ 16 Single-ended	15 Differential/ 30 Single-ended	15 Differential
Voltage Input Range	±1.25, ±2.5, ±5 V, ±10 V		-
Current Input Range	±20 mA (Requires Optional External 125 Ω Resistor)		±20 mA
Resolution	14-bit		
Sample Rate	Single Channel Polling Mode :100K S/s Single Channel Interrupt Mode: 50K S/s 15-channel Scan Mode : 16 K S/s		
Accuracy	0.1% of FSR		
Input Bandwidth	100 KHz		
Zero Drift	± 0.1 uV/°C		
Span Drift	± 10 ppm/°C		
Input Impedance	20 K, 200 K, 20 M (Jumper Select)		-
LED Indicators			
System LED Indicator	1 LED as Power Indicator		
I/O LED Indicator	16 LED as Status Indicator		
EMS Protection			
ESD (IEC 61000-4-2)	±4 kV Contact for each Terminal ±8 kV Air for Random Point		
Isolation			
Intra-module Isolation, Field-to-Logic	2500 Vrms		
Power			
Power Consumption	2 W Max.		
Mechanical			
Dimension (L x W x H)	144 mm x 30.3 mm x 134 mm		
Environment			
Operating Temperature	-25 °C ~ +75°C		
Storage Temperature	-40°C ~ +85°C		
Humidity	10 % ~ 90% RH, non-condensing		


1.2. Pin Assignments

I-8017HW:




Terminal No.	Pin Assignment Name	
	Differential	Single-ended
01	Trig	Trig
02	AGND	AGND
03	Vin0 +	Vin0
04	Vin0 -	Vin8
05	Vin1 +	Vin1
06	Vin1 -	Vin9
07	Vin2 +	Vin2
08	Vin2 -	Vin10
09	Vin3 +	Vin3
10	Vin3 -	Vin11
11	Vin4 +	Vin4
12	Vin4 -	Vin12
13	Vin5 +	Vin5
14	Vin5 -	Vin13
15	Vin6 +	Vin6
16	Vin6 -	Vin14
17	Vin7 +	Vin7
18	Vin7 -	Vin15
19	AGND	AGND
20	AGND	AGND

I-8017HCW:



Terminal No.	Pin Assignment	
	Differential	Single-ended
01	Trig	Trig
02	AGND	AGND
03	Vin0+	Vin0
04	Vin0-	Vin8
05	Vin1+	Vin1
06	Vin1-	Vin9
07	Vin2+	Vin2
08	Vin2-	Vin10
09	Vin3+	Vin3
10	Vin3-	Vin11
11	Vin4+	Vin4
12	Vin4-	Vin12
13	Vin5+	Vin5
14	Vin5-	Vin13
15	Vin6+	Vin6
16	Vin6-	Vin14
17	Vin7+	Vin7
18	Vin7-	Vin15
19	AGND	AGND
20	AGND	AGND


I-8017DW:




Pin Assignment		Terminal No.	Pin Assignment	
Differential	Single-ended		Differential	Single-ended
AGND	AGND	19	37	BK Sensor
Trig	Trig	18	36	-
AI7-	AI15	17	35	-
AI7+	AI7	16	34	-
AI6-	AI14	15	33	-
AI6+	AI6	14	32	-
AI5-	AI13	13	31	-
AI5+	AI5	12	30	-
AI4-	AI12	11	29	-
AI4+	AI4	10	28	-
AI3-	AI11	09	27	-
AI3+	AI3	08	26	-
AI2-	AI10	07	25	-
AI2+	AI2	06	24	-
AI1-	AI9	05	23	-
AI1+	AI1	04	22	-
AI0-	AI8	03	21	AGND
AI0+	AI0	02	20	AGND
BK Sensor	BK Sensor	01		

I-9017:



Pin Assignment		Terminal No.		Pin Assignment		
Differential	Single-ended			Differential	Single-ended	
Trig+	Trig+	1		11	Trig-	Trig-
V0+(I0+)	Vin0	2		12	V0-(I0-)	Vin8
V1+(I1+)	Vin1	3		13	V1-(I1-)	Vin9
V2+(I2+)	Vin2	4		14	V2-(I2-)	Vin10
V3+(I3+)	Vin3	5		15	V3-(I3-)	Vin11
V4+(I4+)	Vin4	6		16	V4-(I4-)	Vin12
V5+(I5+)	Vin5	7		17	V5-(I5-)	Vin13
V6+(I6+)	Vin6	8		18	V6-(I6-)	Vin14
V7+(I7+)	Vin7	9		19	V7-(I7-)	Vin15
AGND	AGND	10		20	AGND	AGND


I-9017-15:



Pin Assignment		Terminal No.		Pin Assignment	
V0+	Vin0	01	17	V0 -	Vin15
V1+	Vin1	02	18	V1 -	Vin16
V2+	Vin2	03	19	V2 -	Vin17
V3+	Vin3	04	20	V3 -	Vin18
V4+	Vin4	05	21	V4 -	Vin19
V5+	Vin5	06	22	V5 -	Vin20
V6+	Vin6	07	23	V6 -	Vin21
V7+	Vin7	08	24	V7 -	Vin22
V8+	Vin8	09	25	V8 -	Vin23
V9+	Vin9	10	26	V9 -	Vin24
V10+	Vin10	11	27	V10 -	Vin25
V11+	Vin11	12	28	V11 -	Vin26
V12+	Vin12	13	29	V12 -	Vin27
V13+	Vin13	14	30	V13 -	Vin28
V14+	Vin14	15	31	V14 -	Vin29
AGND	AGND	16	32	AGND	AGND

32-pin Connector



I-9017C-15:



1.3. Jumper Settings


I-8017HW

Single-ended and Differential Jumper:



This jumper is used to set the discrete input circuits as either “Single-ended” or “Differential” inputs.

Adjusting the Input impedance



Select Input Impedance: 200 k Ω (Default)

Note: 1. The Jumpers should set on the same value
2. Input Impedance = 2 x setting value



The I-8017 series modules allows three input impedance options including as 20 k Ω , 200k Ω (the default setting) and 20M Ω to meet system requirements.

In most cases, 200k Ω is sufficient. Note that each time the input impedance is adjusted on a calibrated module, the module must be recalibrated. For more details, refer to the relevant Calibration information, which can be found in Section 5.1 if you are using either an I-8000 or iPAC-8000 (MiniOS7 platform) controller, or in Section 5.2 if you are using a WinCE or WES platform unit.



I-8017HCW /I-8017DW/ I-9017

125Ω Resistor Jumper

By default, the I-8017HCW module is configured for current source measurement, and the I-8017DW is configured for voltage measurement, as illustrated below:





The default jumper position for current measurement on the I-8017HCW



The default jumper position for voltage measurement on the I-8017DW





The jumper settings used to adjust both the input impedance and the single-ended and differential input on the I-8017HW are the same as those for the I-8017DW, I-8017HCW and the I-9017.



The default jumper position for voltage measurement on the I-9017

1.4. Wire Connections

I-9017





	Voltage Input Wiring	Current Input Wiring
Differential		
Single-ended		

Note:

Differential Input Type: Current Input Wiring need to jumper at current input.

Single-ended Input Type: Current Input Wiring need to jumper at voltage input, an options external 125 Ω resistor is required.





I-8017HW/I-9017-15:

	Voltage Input Wiring	Current Input Wiring
Differential		
Single-ended		

Note:

When connecting to a current source, an optional external 125 Ω resistor is required.

I-8017DW/I-8017HCW


	Voltage Input Wiring	Current Input Wiring
Differential	 The diagram shows a voltage source labeled 'mV/V' with a '+' sign at the top and a '-' sign at the bottom. The positive terminal is connected to the top input of a differential input module, which is labeled 'Vin+' on the right. The negative terminal is connected to the bottom input, labeled 'Vin-' on the right. The module has two input ports on the left, each with a circle and a horizontal line.	 The diagram shows a current source (a circle with an upward arrow) connected in series with a resistor. This combination is connected to the top input of a differential input module, labeled 'Vin+' on the right. The bottom input is labeled 'Vin-' on the right. The module has two input ports on the left, each with a circle and a horizontal line.
Single-ended	 The diagram shows a voltage source labeled 'mV/V' with a '+' sign at the top and a '-' sign at the bottom. The positive terminal is connected to the top input of a single-ended input module, labeled 'Vin' on the right. The negative terminal is connected to the bottom input, labeled 'AGND' on the right. The module has two input ports on the left, each with a circle and a horizontal line.	 The diagram shows a current source (a circle with an upward arrow) connected in series with a resistor labeled '125Ω'. This combination is connected to the top input of a single-ended input module, labeled 'Vin' on the right. The bottom input is labeled 'AGND' on the right. The module has two input ports on the left, each with a circle and a horizontal line.

Note:

Differential Input Type: Current Input Wiring need to jumper at current input.


Single-ended Input Type: Current Input Wiring need to jumper at voltage input, an options external 125 Ω resistor is required.



I-9017C-15

	Current Input Wiring
Differential	 The diagram shows a current source (a circle with an upward arrow) connected in series with a resistor. This combination is connected to the top input of a differential input module, labeled 'I+' on the right. The bottom input is labeled 'I-' on the right. The module has two input ports on the left, each with a circle and a horizontal line.

1.5. Block Diagram

I-8017HW/I-8017DW/I-8017HCW:






2. Quick Start

ICP DAS provides a range of demo programs for different platforms that can be used to verify the functions of the I-8017W/9017. The source code contained in these programs can also be reused in your own custom programs if needed. Both I-8017W/9017 use the same library and demo. The executable file, can be used to retrieve the basic configuration information related to the module and to verify the AI read functions. The basic configuration information includes:

- The version number and the FPGA version
- The Differential/Single-ended jumper settings
- The Gain and Offset values for each input range
- The data read from each channel



1. First, user need to download LinPAC SDK, which includes GNU toolchain, Libraries, header, examples files, etc.
2. Check the power cable, Ethernet cable, VGA monitor, the communication cable between controller and PC has been connected well, and then check the i-8017W/9017 has been plugged in the controller.
3. Refer to the Jumper Settings section. Ensure that the Differential/Single-ended selection jumper is in the Differential position.
4. Connect a stable signal source to the module (e.g., a battery output) using the differential wiring method, as illustrated below.



5. Next, check the communication between controller and PC is fine, and download the demo program files to the controller.

3. Demo Programs

ICP DAS provides a range of demo programs for different platforms that can be used to verify the functions of the module. The source code contained in these programs can also be reused in your own custom programs if needed.

User can find the related files in the product CD or below website:

http://www.icpdas.com/root/product/solutions/pac/linpac/linpac-8000_download.html

or

<http://newweb.icpdas.com/en/download/index.php?kind=8>

4.API References

ICPDAS supplies a range of C API functions for the I-8017W/9017 module. The following is an overview of the functions provided in the LinPAC library - libi8k.a. Detailed information related to individual functions can be found in the following sections.

Platform	Product included	API prefix characters
Linux	I-8017/8017H/8017HW series	"I8017W_" + function name
	I-9017	"I9017_" + function name

API for I-8017HW series and I-9017 series

Function	Description
I8017_Init	Used to initialize the module
I8017_GetFirmwareVersion	Used to read the firmware (FPGA) version information
I8017_GetLibVersion	Used to read the version and build information for the currently installed Library
I8017_GetSingleEndJumper	Used to read the status of the input jumper (Differential or Single-ended mode)
I8017_ReadAI	Used to read the Analog Input value from a specific channel in float format
I8017_ReadAI_AVG	Used to read the average Analog input value from a specific channel in float format
I8017_ReadAIHex	Used to read the Analog Input value from a specific channel in 16-bit hexadecimal format
I8017_ReadAIHex_AVG	Used to read the average Analog input value from a specific channel in hexadecimal format
I8017_ReadGainOffset_Info	Used to read the calibrated voltage Gain and Offset values
I8017_Read_mA_GainOffset	Used to read the calibrated currents Gain and Offset values

API for I-9017-15 only

Function	Description
I8017_Select_SingleEnd	Used to set the Single-ended/ differential mode of I-9017-15.

API for I-8017DW

Function	Description
I8017_Get_D_Sub_Status	Used to get connector status between D sub and 8017DW.

4.1. I8017_Init

This function is used to initialize the module and must be called at least once before using any other function.

Syntax

```
short I8017_Init(  
    int slot  
);
```

Parameters

slot:

specifies the slot number (1 ~ 8).

Return Values

Refer to Appendix A: “Error Code” for more details.

Examples

[C]

```
int slot;  
Open_Slot(slot);  
  
I8017_Init(slot);
```

4.2. I8017_GetFirmwareVersion

This function is used to read the firmware (FPGA) version information for the module.

Syntax

```
short  I8017_GetFirmwareVersion(  
    int slot,  
    short* firmware  
);
```

Parameters

slot

specifies the slot number (1 ~ 8).

**firmware*

[Output]The firmware version information for the I-8017 module.

Return Values

Refer to Appendix A: “Error Code” for more details.

Examples

[C]

```
int slot;  
short firmware;  
Open_Slot(slot);  
  
I8017_GetFirmwareVersion(slot, &firmware);
```

4.3. I8017_GetLibVersion

This function is used to read the version and build information for the Library.

Syntax

```
short I8017_GetLibVersion(void);
```

Parameters

None

Return Values

The version number and build information for the Library used by the module.

Others: Refer to Appendix A: “Error Code Definitions” for more details.

Examples

[C]

```
short version;  
Open_Slot(slot);  
  
version = I8017_GetLibVersion();
```

4.4. I8017_GetSingleEndJumper

This function is used to read whether the jumper is set to either Differential or Single-ended mode.

Syntax

```
short I8017_GetSingleEndJumper(  
    int iSlot,  
    short* selectJumper  
);
```

Parameters

iSlot

specifies the slot number (1 ~ 8).

**selectJumper*

[Output] The status of module.

0: Differential Mode

1: Single-ended Mode

Return Values

Refer to Appendix A: “Error Code” for more details.

Examples

[C]

```
int slot, jumper;  
Open_Slot(slot);  
  
I8017_GetSingleEndJumper(slot, & jumper);
```

Note: The old version LinPAC SDK will show I8017_GetSingleEndJumper(slot) function in demo, if you want to use new I8017_GetSingleEndJumper(slot, & jumper) function, it is necessary to install the latest SDK and recompile your examples.

4.5. I8017_ReadAI

This function is used to read the Analog Input value in float format from a specific channel of the module.

Syntax

```
short I8017HW_ReadAI(  
    int iSlot,  
    int iChannel,  
    int iGain,  
    float* fValue  
);
```

Parameters

iSlot

specifies the slot number (1 ~ 8).

iChannel

Specifies the channel number

iGain

Specifies the input range

0: +/- 10.0V

1: +/- 5.0V

2: +/- 2.5V

3: +/- 1.25V

4: +/- 20mA

** fValue*

[Output] the analog input value in float format.

Return Values

Others: Refer to Appendix A: "Error Code" for more details.

Examples

[C]

```
int slot, ch, gain;  
float fValue;  
Open_Slot(slot);  
  
I8017_ReadAI(slot, ch, gain,& fValue);
```

4.6. I8017_ReadAI_AVG

This function is used to read the average Analog Input value in float format from the module.

Syntax

```
short I8017_ReadAI_AVG(  
    int slot,  
    int iChannel,  
    int iGain,  
    unsigned short averageCnt,  
    float* fValue  
);
```

Parameters

Slot

specifies the slot number (1 ~ 8).

iChannel

Specifies the channel number

iGain

Specifies the input range

0: +/- 10.0V

1: +/- 5.0V

2: +/- 2.5V

3: +/- 1.25V

4: +/- 20mA

averageCnt

the average count for each sampling routine.

**fValue*

[Output] the analog input value in float format.

Return Values

Others: Refer to Appendix A: "Error Code" for more details.

Examples

[C]

```
int slot, ch, gain;  
unsigned short cnt;  
float fValue;  
Open_Slot(slot);  
  
I8017_ReadAI_AVG(slot, ch, gain, cnt,& fValue);
```

4.7. I8017_ReadAIHex

This function is used to read the Analog Input value in 16-bit hexadecimal format.

Syntax

```
short I8017_ReadAIHex(  
    int iSlot,  
    int iChannel,  
    int iGain,  
    short* iValue  
);
```

Parameters

iSlot

specifies the slot number (1 ~ 8).

iChannel

Specifies the channel number

iGain

Specifies the input range

0: +/- 10.0V

1: +/- 5.0V

2: +/- 2.5V

3: +/- 1.25V

4: +/- 20mA

* *iValue*

[Output] the analog input value in hexadecimal format.

Return Values

Others: Refer to Appendix A: "Error Code" for more details.

Examples

[C]

```
int slot, ch, gain;  
short hval;  
Open_Slot(slot);  
  
I8017_ReadAIHex(slot, ch, gain,& hval);
```

Note

the I-8017HW/I-8017DW/I-8017HCW/I-9017/I-9017-15/I-9017C-15 modules use a 14-bit AD chip, when user needs to scale the hexadecimal data ,it is convenient to use the I8017_ReadHex function to return a 16-bit data.

4.8. I8017_ReadAIHex_AVG

This function is used to read the average Analog Input value in 16-bit hexadecimal format.

Syntax

```
short I8017HW_ReadAIHex_AVG(  
    int slot,  
    int iChannel,  
    int iGain,  
    unsigned short averageCnt,  
    short* iValue  
);
```

Parameters

slot

specifies the slot number (1 ~ 8).

iChannel

Specifies the channel number

iGain

Specifies the input range

0: +/- 10.0V

1: +/- 5.0V

2: +/- 2.5V

3: +/- 1.25V

4: +/- 20mA

averageCnt

the average count for each sampling routine.

**iValue*

[Output] the analog input value in hexadecimal format.

Return Values

Others: Refer to Appendix A: "Error Code" for more details.

Examples

[C]

```
int slot, ch, gain;  
unsigned short cnt;  
short hval;  
Open_Slot(slot);  
  
I8017_ReadAIHex_AVG(slot, ch, gain, cnt,& hval);
```

4.9. I8017_ReadGainOffset_Info

This function is used to read the calibrated Gain and Offset values for the I-8017 module inserted in a specific slot

Syntax

```
short I8017_ReadGainOffset_Info(  
    int iSlot,  
    int iGain,  
    unsigned short* iGainValue,  
    short* iOffsetValue  
);
```

Parameters

iSlot

specifies the slot number (1 ~ 8).

iGain

Specifies the input range

0: +/- 10.0V

1: +/- 5.0V

2: +/- 2.5V

3: +/- 1.25V

4: +/- 20mA

**iGainValue*

[Output] Specifies the calibrated Gain value

**iOffsetValue*

[Output] Specifies the calibrated Offset value

Return Values

Refer to Appendix A: "Error Code" for more details.

Examples

[C]

```
Int slot, Gain;  
unsigned short GainValue;  
short OffsetValue;  
Open_Slot(slot);  
  
I8017_ReadGainOffset_Info(slot, Gain, & GainValue, & OffsetValue);
```

4.10. I8017_Read_mA_GainOffset

This function is used to read the calibrated Gain and Offset values for the I-8017HCW/I-9017/I-9017C-15 module inserted in a specific slot.

Syntax

```
short I8017_Read_mA_GainOffset(  
    int slot,  
    short ch,  
    unsigned short* GainValue,  
    short* offsetValue  
);
```

Parameters

slot

specifies the slot number (1 ~ 8).

ch

Specifies the channel

Valid range :

I-8017HCW/I-9017 = 0 to 7

I-9017C-15 = 0 to 14

* *GainValue*

Specifies the calibrated Gain value

* *offsetValue*

Specifies the calibrated Offset value

Return Values

Refer to Appendix A: "Error Code" for more details.

Examples

[C]

```
int slot;  
short ch;  
unsigned short GainValue;  
short OffsetValue;  
Open_Slot(slot);  
  
I8017_Read_mA_GainOffset(slot, ch,& GainValue, & OffsetValue);
```

4.11. I8017_Select_SingleEnd

This function is used to set the Single-ended/ differential mode of I-9017-15.

Syntax

```
short I8017_Select_SingleEnd (  
    int slot,  
    short selection  
);
```

Parameters

slot

specifies the slot number (1 ~ 8).

selection

The status of module.

0: Differential Mode

1: Single-ended Mode

Return Values

Refer to Appendix A: “Error Code” for more details.

Examples

[C]

```
int slot;  
short status;  
Open_Slot(slot);  
  
I8017_Select_SingleEnd(slot, status);
```

4.12. I8017_Get_D_Sub_Status

This function is used to get connector status between D sub and 8017DW.

Syntax

```
short I8017_Get_D_Sub_Status(  
    int iSlot,  
    short* D_Sub_Status  
);
```

Parameters

slot

specifies the slot number (1 ~ 8).

**D_Sub_Status*

The status of D_Sub.

1 : Open

0 : Close

Return Values

Refer to Appendix A: "Error Code" for more details.

Note

function for I-8017DW module only, in the others 8017 series module,
the value of D Sub Status will always be 1.

Examples

[C]

```
int slot;  
short status;  
Open_Slot(slot);  
  
I8017_Get_D_Sub_Status (slot, status);
```

5. Troubleshooting

This chapter discusses how to solve some common problems you may encounter.

This chapter contains:

- What to do when the data read from the module seems unstable

5.1. Service Request Requirements

If you are using a stable signal source to output a signal to the module, such as a battery, and are receiving incorrect or unstable data, prepare the following three items and e-mail them to service@icpdas.com

- An image of the physical wiring
- The file saved from the Basic Information tab
- The file saved from the AI Test tab


5.2. What to do when the data read from the module seems unstable

If the voltage can be measured correctly when testing using a battery, but not when using the real signal source, the error may be caused by any or all of the following factors:

- A noise-corrupted signal source
- Instability in the signal source
- A floating signal source that is not referenced to a system ground(earth or building ground)

Because of the nature of the high-speed data acquisition function on the module, any noise coupled to a signal, or any change in voltage on an unstable source, is also captured. In this situation, signal filtering or isolation should be considered in order to enhance the quality of the signal.

It is recommended that the V- pin is connected to the AGND (system ground) pin when measuring differential signals, as shown in the figure below.



Appendix A. Error Code

Error Code	Definition	Description
0	NoError	This indicates that there have been no errors
-1	ID_ERROR	There is a problem with the module ID
-2	SLOT_ERROR	There is a Slot index error (1 ~ 8)
-3	CHANNEL_ERROR	There is a Channel index error (0 ~ 15)
-4	GAIN_ERROR	There is a Gain error (0 ~ 4)
-6	NOT_SUPPORT_ERROR	The function is not support the Firmware
-7	NOT_Calibration	The module is not calibrated